

# POWERFULFOREX

## Requirements

PowerfulForex EA works on MetaTrader 4 terminal only. It was created for trading on AUDUSD currency pair. Minimal deposit is \$190 for lot 0.01.

Recommended leverage is from 1:100 (bigger leverage is better for reliability).

Contact our support ([support@powerfulforex.com](mailto:support@powerfulforex.com)) if your parameters are lower than the requirements above.

## Quick start

- ▶ Run your MetaTrader 4 terminal.
- ▶ Open menu “Files”, then “Open Data Folder”.
- ▶ Copy the EA’s files from the archive into data folder of your MetaTrader 4 terminal:
  - ex4 file to MQL\Experts
  - dll file to MQL\Libraries


(more detailed information about the necessary folders is [here](#))

- ▶ Restart your MetaTrader 4 terminal.
- ▶ Attach PowerfulForex from the Navigator panel to the AUDUSD H1 chart.
- ▶ Allow “Live trading” and “DLL imports” in Common settings.


(example of the correctly selected Common settings is [here](#))

- ▶ Leave the default values of Input settings or set the desired values there.
  - (explanation of PowerfulForex parameters is [here](#))
- ▶ Make sure that “AutoTrading” is enabled on your MetaTrader 4 terminal.

## How to find the “Experts” and “Libraries” folders



## How to allow “Live trading” and “DLL imports”



## The explanation of PowerfulForex parameters

**AutoRisk** is a percentage of your deposit based on which the EA calculates the first lot. Other lots are based on that first lot. Recommended value is up to 1%.

**Lot** is the first lot, which you can set manually. It works only if AutoRisk=0

**MaxOrders** is a maximal number of loss orders in a row. After the last one the EA opens the first lot again.

**AccountMicro** is a multiplication of the first lot by 10. Needed for micro accounts only. Do not enable it unless you know well what you are doing.

**AutoGMT** is an auto detection of your broker's GMT.

**YourGMT** is a GMT, which you can set manually. It works only if AutoGMT=false

**Magic** is a magic number.

**Slippage** means slippage. Do not change it unless you know well what you are doing.

Contact our support ([support@powerfulforex.com](mailto:support@powerfulforex.com)) if you have any questions.

